

# **Angel Class Dynamic Processors for Merging Technologies Pyramix DAW**

## Table of Contents

<b>Welcome</b>	<b>1</b>
<b>Solera</b>	<b>2</b>
<b>Pure Compressor</b>	<b>6</b>
<b>Pure Expander</b>	<b>7</b>
<b>Pure DCompressor</b>	<b>8</b>
<b>Pure DExpander</b>	<b>9</b>
<b>Preset Management</b>	<b>10</b>
<b>Automation</b>	<b>12</b>
<b>Index</b>	<b>a</b>

# 1 Welcome

We are very proud to introduce a new range of dynamic processors for the Merging Technologies' Pyramix DAW.

The "Angel Class Dynamic Processor" family features the all-in-one "Solera", the "Pure Compressor", the "Pure Expander", the "Pure DCompressor", the "Pure DExpander".

Solera is the flag ship of the Angel Class Dynamic Processors. It is primarily designed for mastering and re-mastering applications. However, it can also be used as a regular dynamic processor for superior sonic quality and distortion free operation.

Every Angel Class Dynamic Processor plug-in uses some exclusive algorithms that endows them with an incredibly clear and natural sound.

The Pure series uses the same technologies for specific dynamic processes.

Here are some of the key features that make our plug-in the best available for dynamic processing in the digital domain:

1. An analog like metering. RMS values are more useful than dB-fs when setting a dynamic processor.
2. The "Angel's Share" parameter takes account of the signal for intelligent relaxation of the compressor action.
3. The "Hysteresis" parameter allows compressing and de-compressing independently of the sound level and can be mixed with the standard compression scheme
4. The Auto Release features an unique algorithm that avoids typical pumping effect.
5. A delay line can inserted in the signal path to produce a null attack time.
6. The A/B compare and Morphing section enables ultra fast and precise operations.

The "Angel Class Dynamic Processor family supports up to simultaneous 8 channels and DXD operations and ensures the best audio quality ever.

## 2 Solera

Solera comes from 10-years-long cogitation about the compression, the dynamic, the loudness. How to make a compressor which can add loudness whilst keeping some airiness in the sound, which retains fast transients, subtle distinction and undertone etc ? How to make a processor that can retrieve lost dynamic? Or just to be able to add contrast, to increase low level ambiance or to sharpen the sound etc... How can we imagine doing without sound Level to compress the sound constantly without losing the “nuance” nor pumping? And so more questions.

Thanks to Yves, Jérôme, Graemme, Laurent, Rodolphe and Ronald for all the discussions which largely contributed to finding a solution.

Thanks to George Massenburg for his Model 8900 which opened the ways.

Solera implements 4 different detectors and envelop generators in parallel and simultaneous: compressor, de-compressor, expander and de-expander. All can be independently switched on or off [25](#) and implement an activity display [26](#) near to their controls. For each you can set the threshold [27](#), the ratio [28](#) and a knee [29](#) (hard to very soft knee).

On top of these controls you’ll find a display area that show you the resultant dynamic curve and from left to right, the Input level [7](#) (vu-meter not peak-meter, referenced to -16 dB FS), the Output level [8](#), the resultant envelop [10](#) (compression, decompression), the dynamic difference between in and out [11](#) and the level difference between in and out [12](#). Just under these meters, you find the dynamic meter [13](#) (in orange) and another one [14](#) (blue segment) which represent the release variation in auto-release mode (variation between fast release on the left to slow release on the right). There’s also a parametric curve for the side-chain EQ [15](#), [32](#), [34](#), [36](#), [37](#).

To finalize the description of the standard things; there’s an Input level [3](#), an Output level [4](#), a Bypass [1](#), a Clipper [2](#) (brick wall limiter to 0 dB FS) and an EQ section (which is only applied to the detection channel if you don’t enable the Solo function [33](#)).



5 Displays the overall **transfer curve** for the current settings including all active dynamic sections of the Solera.

6 Displays the **scale** for the transfer curve. It is automatically adjusted to the threshold settings

7 & 8 When MS mode is enabled, the M level is displayed on the left vu and the S level is displayed on the right vu.

15 is the **graphic display** for the detector EQ section. This curve can be set directly with the mouse if the EQ section is enabled. A right-click allows you to adjust the Q-factor with the mouse.

16 **Delay**: Enables the delay line on the signal path allowing you to sync the signal processing to the detection scheme which is done in RMS with an integration time equal to the attack time.

17 The **Auto** function set the delay automatically which produce a dynamic processing with an “attack zero”. The attack settings will therefore be used to speed up or slow down the integration time

18 sets the **Attack Time** for all dynamic process. It also sets the delay line value if Auto is enabled for delay.

19 **Release Mode**: Auto Release & Advanced Auto Release: In Auto Release all is done automatically and solera will try to

match the release to the audio material. In Advance Auto-Release, you will be able to indicate to the auto-release engine the action range: Release gives Release Maximum, the slower possible and release Minimum is the faster one. You can also set the velocity of the engine (variation speed).

**20** sets the **Release** value for the manual mode and maximum release value in advanced mode.

**21** sets the **Minimum release** value in advanced mode.

**22** sets the **Velocity** of the release value variation in advanced mode.

**23** sets the **Width** of the stereo signal when the MS mode is activated. A 0.00 value produces no changing. A -6 value produces a mono output.

**24 MS** (only in 2 channels): Solera will encode the input signal in MS, make his processing then decode back to stereo while applying the clipper (if on). The MS Width allows expanding or shrinking the stereo width.

**30 Angel's Share:** to literally open the sound, increase the dynamic impression, keep some crest etc.

**31 Hysteresis:** allows compressing and de-compressing independently of the sound level and can be mixed with the standard compression scheme; the second magic button. This setting doesn't act on the expander and the de-expander.

**38** is the **display and edit** area for the preset name.

**39** is the **browser** for presets.

**40** saves the preset in its current state.

**41** recalls the selected preset.

**42** There are two preset slots to store and recall settings; with a "**Morphing Slider**" in between to go from one to another preset. Double click on the slider to directly switch between A and B. Right click on the display Area to import or export preset and right click on a control to set the automation mode, reset it to the default value, Inc or Dec it and store/recall independent value.

Using **Ctrl key** constrains the value variation of controls to 6 dB for levels, 100 Hz for frequencies, and 1 dB for ratio.


***Solera** is a wine making technique: A solera is method of fractional blending for wine, closely paralleling the making of Sherry or Malaga. A solera consists of several rows of stacked oak barrels with the oldest wine in the bottom row and the most recently made at the top. At bottling, about one-third of the wine in the bottom row is removed and wine from the row just above replaces it and soon, until reaching the top row, which is replenished with new wine. The concept behind a solera is to make a wine that remains consistent from year to year.*

**Angel's Share** is a term used for Armagnac, Cognac, Whisky; that part of the spirit that evaporates during the process of aging.

## 3 Pure Compressor

Pure Compressor is the compressor section of the Solera

The advanced mode for release is only available on the Solera.




Please refer to the Solera section for a complete description of the settings.



# 4 Pure Expander

Pure Compressor is the expander section of the Solera

The advanced mode for release is only available on the Solera.



Please refer to the Solera section for a complete description of the settings.

# 5 Pure DCompressor

Pure Compressor is the de-compressor section of the Solera

The advanced mode for release is only available on the Solera.



Please refer to the Solera section for a complete description of the settings.

# 6 Pure DExpander

Pure Compressor is the de-expander section of the Solera

The advanced mode for release is only available on the Solera.




Please refer to the Solera section for a complete description of the settings.

# 7 Preset Management

Solera allows users to have a bank of five presets for every setting.

A right-click on the control displays the specific panel to manage individual setting presets.



Solera allows users to compare and morph between 2 global presets.

**To recall a preset** in the A or the B section:

1. Click on the browser button of the corresponding section.
2. Select the desired preset in the shared preset bank.
3. Press the recall button.



**To create a new preset:**

1. Click on the browser button.
2. Select an empty preset or a redundant one.
3. Enter a name for this new preset.
4. Press the save button.

CenteredImage3



A double-click on the morphing slider area produces an instant A/B compare. If the slider is moved from A to B, all the settings are interpolated from one value to another allowing to the user set all parameters at one time with a single mouse action. Of course an in-between setting can be stored as new global preset.



As usual for Pyramix' plug-in, global presets can be imported and exported with a right-click on the plug-in's container.

# 8 Automation

Every control can be automated except the morphing fader.

A right-click on the control display the panel for automation.



A black square means that the control is in Isolate mode.

A green square means that the control is in Play mode.

A red square means that the control is in Record mode.

By default all controllers are in Auto-Write mode.

## Index

### A

Automation 12

### P

Preset Management 10

Pure Compressor 6

Pure DCompressor 8

Pure DExpander 9

Pure Expander 7

### S

Solera 2

### W

Welcome 1